

S.NO.	PROCESS OF SIGNUP & DOWNLOAD TP CLIENT & PATCH	Screenshot No.
Configuration	Windows XP/ 7/8/8.1 (32/64-bit operating system) , basic softwares - Ms Office,Win Rar (any version) and Autocad /Progecad (2006-2014)	
STEP 1	Go to our website- "bpms.sudacg.in" and select municipal corporation in which you want to work, and log-in.	1
STEP 2	After log-in, in the right upper most side of the page find "sign up",and click on it.	2
STEP 3	After clicking "sign up" fill all details of Architect sign up form. (* mark fields are Mandatory)	3
STEP 4	After filling details Upload your "Certificate from GOI" and "degree cert." in pdf format,size not exceeding then 2 mb.	4
STEP 5	Submit these details, "terms and condition" page will be open, accept the terms and conditions and submit.	5
STEP 6	After clicking on submit, a message will display-"sign up successfully".	6
STEP 7	After this process you'll provided id and password through your email-id given in sign up form,by Admin.	7 & 8
STEP 8	Now login with your id & password.	7 & 8
STEP 9	After login in the right side you'll find links for, Download TP Client, Download TP Client Patch, Download DC Rules, Hindi Translation	9
STEP 10	Go to the setup of "TP Client" and right click on the setup file and select "open" and then run the setup.	
STEP 11	<p>After the installation is completed.Go to "C:\TPClient\Soft\VB" and open the "acad path" file and then change from "C:\Program Files\Autodesk\AutoCAD 2012 - English\acad.exe 2008" to "C:\Program Files\AutoCAD 2010\acad.exe 2008" and save it and close it. (you can change the vesrion of autocad according to your autocad version)</p>	
Note-	If in case TPClient is not opeing properly then you have to Copy the windows missing file to c:Windows/system 32 and register it	
	Steps of Registering the windows file.	
STEP 1	Copy the windows missing file from "Missing files of Windows" folder and paste it to "C:\Windows\System32"	
STEP 2	Go to Start-All files-Accessories-Command Prompt-and right click on it and "run it as administrator"	
STEP 3	Do like this in command prompt - "C:\Windows\System32>regsvr32 C:\Windows\System32\comctl32.ocx"	
	Similarly do "C:\Windows\System32>regsvr32 C:\Windows\System32\COMDLG32.OCX"	
	and "C:\Windows\System32>regsvr32 C:\Windows\System32\MSCOMCTL.OCX"	
	and "C:\Windows\System32>regsvr32 C:\Windows\System32\MSFLXGRD.OCX"	
	and "C:\Windows\System32>regsvr32 C:\Windows\System32\tabctl32.ocx"	
	[TPClient][53] Flie not found Error- Go to "C:\TPClient\Soft\VB" and open "acadpath.txt" file and change the path of autocad according to the version you are using	